

Hemisson Modules

Serial Command Guide

September 15th 2004



RoadNarrows LLC

RoadNarrows LLC

<http://www.roadnarrowsrobotics.com/>

<mailto:oneway@roadnarrowsrobotics.com>

NOTICE

The authors of this guide have used their best efforts in preparing and validating the accuracy contained within. The authors and RoadNarrows LLC make no warranty of any kind, expressed or implied, with regard to this guide's accuracy. The authors and RoadNarrows LLC are not liable nor take any responsibility for any errors found in this guide.

The content of this guide is subject to change without notice.

This guide describes serial commands provided by version 1.50RNc of the HemiOS to access and control Hemisson I2C capable modules connected to the robot base. Serial commands may be sent by a host computer and responses received either 1) via a cabled connection to the Hemisson RS232 serial port or 2) wirelessly via the Hemisson Bluetooth Serial Module.

Symbol	Description
←	ASCII Carriage Return CR (0x0D). All commands sent to the Hemisson end with a CR ←.
↓	ASCII Newline NL (0x0A). All responses from the Hemisson are terminated with CR-NL ←↓ pair.
<i>h</i>	ASCII hexadecimal digit: 'a' – 'f', 'A' – 'F', '0' – '9'
<i>d</i>	ASCII decimal digit: '0' – '9'
<i>b</i>	ASCII binary digit: '0', '1'
<i>val</i>	Variable ASCII value.
A, B, ...	ASCII literal character 'A', 'B', ... All commands are upper case, single letter non-whitespace, printable characters.
a, b, ...	ASCII literal character 'a', 'b', ... All responses are lower case equivalents to their respective commands.
,	ASCII Comma (0x2C). Command/response field separator.
[]	Optional arguments to command or values in the response.
...	Zero or more following arguments.

Table 1: Notation

Each I2C module supports a set of commands specific to that module (see the following sections). To issue a module command, the following command/response syntax is used.

Command: *A,m,c[,cmdarg...]* ←

Response: *a,m,r[,rspval...]* ← ↓

Arguments/Values:

- m* Unique, one-character module identifier (see Table 2)
- c* Specific, single-letter, upper case module command.
- cmdarg* Optional command argument. Specific to each command.
- r* Response identifier. Lower case equivalent to command.
- rspval* Optional response value. Specific to each response.

Module	Identifier	Notes
BasicStamp II	2	Module not available yet.
Bluetooth Serial	-	Not I2C capable.
General I/O	G	Available.
LCD	D	RN HemiOS support not available yet.
Linear Camera	L	RN HemiOS support not available yet.
Text-To-Speech	T	Available.
UltraSonic Sensor	U	RN HemiOS support not available yet.
Wireless Color Camera	-	Not I2C capable.

Table 2: Module Summary

The J command is useful to discover which I2C modules are connected to the Hemisson robot base.

J Scan all I2C addresses for all connected I2C capable modules.

Command: J ←

Response: j[,m,addr,ver[,...]] ← ↓

Arguments/Values:

m Unique, one-character module identifier.
 Format: see Table 2.

addr Hexidecimal base I2C address of the module.
 Format: *hh*.

ver Hexidecimal version number of the module.
 Format: *hh*.

For each discovered module, a triplet of response values are sent.

Module Identifier: **G**

A **Read Analog register**

Command: $A, G, A, reg \leftarrow$

Response: $a, G, a, reg, val \leftarrow \downarrow$

Arguments/Values:

reg Analog register number.
 Format: *hh*.
 Range: 00 – 04 hexadecimal (1 – 4)

val Value of the 8-bit register read.
 Format: *hh*.

Example 1: Read analog register 3, returning the value of 31.

Command: $A, G, A, 03 \leftarrow$ Response: $a, G, a, 03, 1F \leftarrow \downarrow$

Note 1: The analog register address is $0x10 + reg$.

R **Read digital register**

Command: $A, G, R, reg \leftarrow$

Response: $a, G, r, reg, val \leftarrow \downarrow$

Arguments/Values:

reg Digital register number.
 Format: *hh*.
 Range: 00 – 0B hexadecimal (1 – 11)

val Value of the 1-bit register read.
 Format: *b*.

Example 1: Read digital register 10, returning the value of 1.

Command: $A, G, R, 0A \leftarrow$ Response: $a, G, r, 0A, 1 \leftarrow \downarrow$

Note 1: The digital register address is $0x20 + reg$.

W **Write digital register**

Command: $A, G, W, reg, val \leftarrow$

Response: $a, G, w, reg, val \leftarrow \downarrow$

Arguments/Values:

reg Digital register number.
 Format: *hh*.
 Range: 00 – 0B hexadecimal (1 – 11)

val 1-bit value to write.
 Format: *b*.

Example 1: Write the value 0 to digital register 7.

 Command: $A, G, W, 07, 0 \leftarrow$

 Response: $a, G, w, 07, 0 \leftarrow \downarrow$

Note 1: The digital register address is $0x20 + reg$.

V **Get Version number of this module**

Command: $A, G, V \leftarrow$

Response: $a, G, v, vernum \leftarrow \downarrow$

Arguments/Values:

vernum Module version number..
 Format: *hh*.

Example 1: Get the module's version number.

 Command: $A, G, V \leftarrow$

 Response: $a, G, v, 06 \leftarrow \downarrow$

Module Identifier: T

C Speak a Canned message

Command: A,T,C,msgnum ←

Response: a,T,c,msgnum ← ↓

Arguments/Values:

msgnum The number of the pre-stored message.
Format: *hh*.
Range: 01 – 1E hexadecimal (1 – 30)

Example 1: Play canned message number 1.

Command: A,T,C,01 ←

Response: a,T,c,01 ← ↓

Pre-stored messages are loaded into the Text-To-Speech module through the module's serial port using the Window's application SP03.exe. Up to 30 messages may be pre-stored.

Note 1: Text messages are converted and stored using the voice pitch and rate values at the time the text is converted. The pitch and rate module commands have no effect on pre-stored messages.

G Set speaker Gain (volume)

Command: A,T,G,gain ←

Response: a,T,g,gain ← ↓

Arguments/Values:

gain Gain (volume) of the speaker.
Format: *d*.
Range: 0 (loudest) – 7 (quietest)
Default: 0

Example 1: Set the volume to the 'ghetto blaster' level

Command: A,T,G,0 ←

Response: a,T,g,0 ← ↓

Note 1: The speaker has very small range in power. All but loudest settings are virtually inaudible.

P **Set Pitch of voice in text-to-speech conversion**

Command: `A,T,P,pitch ←`

Response: `a,T,p,pitch ← ↓`

Arguments/Values:

pitch Voice pitch of the converted text.
 Format: *d*.
 Range: 0 (highest) – 7 (lowest)
 Default: 5

Example 1: "Mickey Mouse" the voice.

Command: `A,T,P,0 ←`

Response: `a,T,p,0 ← ↓`

Note 1: Setting this value has no effect on pre-stored, canned messages.

Note 2: The pitch value 06 is wierd.

Q **Query if Text-To-Speech module is currently speaking**

Command: `A,T,Q ←`

Response: `a,T,q,state ← ↓`

Arguments/Values:

state TTS module is [not] speaking.
 Format: *b*.
 Enum: 0 (not speaking), 1 (speaking)

Example 1: Query TTS module until it shuts up.

Command: `A,T,S,blah blah ←`

Response: `a,T,s,blah blah ← ↓`

Command: `A,Q ←`

Response: `a,q,1 ← ↓`

Command: `A,Q ←`

Response: `a,q,0 ← ↓`

R Set Rate (speed) of voice in text-to-speech conversion

Command: `A,T,R,rate ←`

Response: `a,T,r,rate ← ↓`

Arguments/Values:

rate Voice rate (speed) of the converted text.
 Format: *d*.
 Range: 0 (slowest) – 3 (fastest)
 Default: 3

Example 1: Speak Southern, y'all.

Command: `A,T,R,0 ←`

Response: `a,T,r,0 ← ↓`

Note 1: Setting this value has no effect on pre-stored, canned messages.

Note 2: Voice rate settings are almost imperceptible.

S Speak a message

Command: `A,T,S,string ←`

Response: `a,T,s,string ← ↓`

Arguments/Values:

string Text message to speak.
 Format: ASCII text. See Table T1.
 Length: 1 – 72 bytes

Example 1: Speak 'H' 'E' 'L' 'L' 'O'.

Command: `A,T,S,HELLO ←`

Response: `a,T,s,HELLO ← ↓`

Example 2: Speak 'Hello Dolly'.

Command: `A,T,S,Hello Dolly ←`

Response: `a,T,s,Hello Dolly ← ↓`

The text will be spoken at the current speaker gain with current voice pitch and rate settings.

Text	Rule
<i>WORD</i>	An all upper case <i>WORD</i> is spoken as an acronym (i.e. each letter is pronounced).
<i>Word</i>	<i>Word</i> is pronounced.
<i>word</i>	<i>word</i> is pronounced.
"',.?!"	Punctuation marks are ignored.

Table T1: Text-To-Speech Conversion Rules

T

Text-To-Speech Module

T

V **Get Version number of this module**

Command: *A,T,V* ←

Response: *a,T,v,vernum* ← ↓

Arguments/Values:

vernum Module version number..

 Format: *hh*.

Example 1: Get the module's version number.

 Command: *A,T,V* ←

 Response: *a,T,v,06* ← ↓